


UPDATED FOR V16



BRICSCAD[®]



SYSTEM VARIABLES

BRISYS

Table of Contents

System Variables and User Preferences	2
To Open the Settings Dialog	2
Understanding the Settings Dialog	3
To Find Settings.....	5
To Edit Settings	5
Editing Settings in the Command Bar	5
To Export Settings	6


System Variables and User Preferences

To see a complete list of all System variables:

1. Type *setvar* in the command window followed by Enter.
The command bar reads: Variable name or ?:
2. Type ? (question mark) in the command bar, then press Enter.
The command bar reads: Variable(s) to list <*>:
3. Press Enter.
The *BricsCAD Prompt History* window opens, listing all variables and their current value.

To Open the Settings Dialog

1. Do one of the following:
 - Click the *Settings* tool button (🔧) on the *Standard* toolbar.
 - Choose *Settings...* in the *Settings* menu.



- Type *settings* in the command bar, then press Enter.
2. (option) Choose a display mode by clicking the corresponding button in the *Settings* toolbar.

Categorized (🗃️)

Lists the settings by category: *Drawing*, *Dimensions* and *Program Options*.

Alphabetical (🔤)

Lists the settings alphabetically.

3. (option) Choose a category:

Drawing (📐)

Opens the *Categorized* view mode, with the *Drawing* tree expanded.

Dimensions (📏)

Opens the *Categorized* view mode, with the *Dimension* tree expanded.

Program Options (⚙️)

Opens the *Categorized* view mode, with the *Program Options* tree expanded.


4. Use the *search* field to [find a setting](#).

Understanding the Settings Dialog







The *Settings* dialog gives you an overview of all System variables and user preferences and their current value.

Here you can:

- Find System variables and user preferences.
- Edit System variables and user preferences.
- Export the properties and the current value of all variables and user preferences to a text file




BricsCAD - System Variables

1	Class: Drawing, Dimensions or Program Options
2	Category (expanded)
3	Sub-category (expanded)
4	Group (expanded)
5	Current value of a system variable
6	Options list
7	<p>Internal Name: System variable names are fully capitalized: LUNITS User preference names are mixed case: TemplatePath You can type system variables and user preferences in the command window to edit them or use the SETVAR command (system variables only).</p>
8	Variable Title
9	Variable Help
10	Preview (if available)
11	Settings Type ( = read-only;  = user-defined)
12	<p>Save location  = drawing  = registry (system variable) ;  = registry (user preference)  = not saved</p>



To Find Settings

1. Open the [Settings Dialog](#).
2. (option) Click the *Find Options* button () to open the *Find Setting* dialog where you can set the search options.



3. Type the search string in the *Search* field.



- The first setting matching the content of the search field highlights.
4. (option) Click the *next* () or *previous* () button to browse through the matching settings.

NOTE If you check all *Find where* options in step 2, it might take longer to find the variable you are looking for, since more variables match the content of the *Find what* field.

To Edit Settings

1. Open the [Settings Dialog](#).
2. [Find](#) a setting.
3. Click the settings field to edit the setting.
4. (option) Repeat steps 2 and 3 to edit more settings.
5. Close the *Settings* window.

Editing Settings in the Command Bar


1. Type the name of the system variable or user preference in the command bar, e.g. *autosnap*

The command bar reads: New current value for AUTOSNAP (0 to 63) <63>:

2. Type the desired value in the command bar, then press Enter.

NOTES

- The value of some system variables is stored as a bitcode using the sum of the values of all selected options.
E.g.: The AUTOCOMPLETEMODE system variable has 5 options: 1 = *Enable*, 2 = *Auto-Append*, 4 = *Suggestion List*, 8 = *Display Icons (unsupported)*, 16 = *Exclude the display of system variables*.
When *Enable*, *Auto-Append* and *Suggestion List* are selected the value of AUTOCOMPLETEMODE = 7 (1 + 2 + 4)
- System variable names are recognized by the *Autocomplete* feature of the command bar if the *Exclude the Display of System Variables* option of the *AUTOCOMPLETEMODE* system variable is not checked.



To Export Settings

1. Click the *Export* tool (L →) on the *Settings* toolbar.
The *Export Settings* window opens.
2. Type a name in the *File name* field.
3. Select a folder.
4. Click the *Save* button on the *Export Settings* window.
All Settings are exported in a CSV (Comma Separated Values) text file, which can be opened in Microsoft® Excel®.